



# Dobot CR Series Robot

## APP User Guide

---

Issue: V3.7

Date: 2020-12-04

**Shenzhen Yuejiang Technology Co., Ltd**

## Precautions

### **Copyright © Shenzhen Yuejiang Technology Co., Ltd 2020. All rights reserved.**

No part of this document may be reproduced or transmitted in any form or by any means without the prior written consent of Yuejiang Technology Co., Ltd.

### **Disclaimer**

To the maximum extent permitted by applicable law, the products described (including its hardware, software, and firmware, etc.) in this document are provided **AS IS**, which may have flaws, errors or faults. Yuejiang makes no warranties of any kind, express or implied, including but not limited to, merchantability, satisfaction of quality, fitness for a particular purpose and non-infringement of third party rights. In no event will Yuejiang be liable for any special, incidental, consequential or indirect damages resulting from the use of our products and documents.

Before using our product, please thoroughly read and understand the contents of this document and related technical documents that are published online, to ensure that the robot is used on the premise of fully understanding the robot and related knowledge. Please use this document with technical guidance from professionals. Even if follow this document or any other related instructions, Damages or losses will be happening in the using process, Dobot shall not be considered as a guarantee regarding all security information contained in this document.

The user has the responsibility to make sure following the relevant practical laws and regulations of the country, in order that there is no significant danger in the use of the robot.

## Shenzhen Yuejiang Technology Co., Ltd

Address: Floor 9-10, Building 2, Chongwen Garden, Nanshan iPark, Liuxian Blvd, Nanshan District, Shenzhen, Guangdong Province, China

Website: [www.dobot.cc](http://www.dobot.cc)

## Preface

### Purpose

This Document describes how to use Dobot CR series robots with APP, making it easy for users to fully understand and use it.

### Intended Audience

This document is intended for:

- Customer
- Sales Engineer
- Installation and Commissioning Engineer
- Technical Support Engineer

### Change History

| Date       | Change Description                            |
|------------|---|
| 2020/12/04 | The second release<br>Add palletizing process |
| 2020/11/17 | The first release                             |

### Symbol Conventions

The symbols that may be founded in this document are defined as follows.

| Symbol  | Description   |
|---|---|
|  DANGER  | Indicates a hazard with a high level of risk which, if not avoided, could result in death or serious injury                               |
|  WARNING | Indicates a hazard with a medium level or low level of risk which, if not avoided, could result in minor or moderate injury, robot damage |
|  NOTICE  | Indicates a potentially hazardous situation which, if not avoided, can result in equipment damage, data loss, or unanticipated result     |
|  NOTE    | Provides additional information to emphasize or supplement important points in the main text  |

## Contents

|   |           |
|---|-----------|
| <b>Precautions .....</b>                        | <b>i</b>  |
| <b>Preface.....</b>                             | <b>ii</b> |
| <b>1. Function Description of Software.....</b> | <b>2</b>  |
| <b>2. Fast Connection.....</b>                  | <b>5</b>  |
| <b>3. Setting.....</b>                          | <b>6</b>  |
| 3.1 Set Jog.....                                | 6         |
| 3.2 Set Playback.....                           | 6         |
| 3.3 Coor User.....                              | 8         |
| 3.4 Coor Tool .....                             | 11        |
| 3.5 Safe Set .....                              | 14        |
| 3.5.1 Safe Collision .....                      | 14        |
| 3.5.2 Electronic Skin .....                     | 14        |
| 3.5.3 Joint Brake.....                          | 15        |
| 3.5.4 Power Control.....                        | 16        |
| 3.5.5 Terminal Load .....                       | 16        |
| 3.6 Remote Control.....                         | 17        |
| 3.6.1 Remote I/O .....                          | 17        |
| 3.6.2 Remote Modbus.....                        | 19        |
| 3.7 Robot Pose .....                            | 21        |
| 3.8 Installation .....                          | 22        |
| 3.9 Manufactory Set.....                        | 23        |
| 3.10 Software Set.....                          | 23        |
| 3.10.1 Lock Set.....                            | 23        |
| 3.10.2 File Import/Export.....                  | 24        |
| 3.10.3 WiFi Set.....                            | 24        |
| 3.10.4 IP Setting .....                         | 25        |
| 3.10.5 User Manager .....                       | 25        |
| <b>4. Process.....</b>                          | <b>27</b> |
| 4.1 Drag Teach .....                            | 27        |
| 4.2 Palletizing .....                           | 28        |
| 4.2.1 Setting Pallet.....                       | 28        |
| 4.2.2 Example.....                              | 32        |
| <b>5. Monitor .....</b>                         | <b>33</b> |
| 5.1 I/O Monitor .....                           | 33        |
| 5.2 Robot Status .....                          | 34        |
| 5.3 Terminal .....                              | 34        |
| 5.3.1 Custom End .....                          | 34        |
| 5.3.2 Terminal Hot Key .....                    | 36        |
| <b>6. Programming.....</b>                      | <b>38</b> |
| 6.1 Project Description.....                    | 38        |
| 6.2 Program Description .....                   | 38        |
| 6.3 Program Example.....                        | 41        |

## 1. Function Description of Software

The robot supports Android/iOS tablet operation and PC operation. This manual uses Android tablet as an example.

The interface is shown in Figure 1.1, and its detailed description is shown in Table 3.1.




Figure 1.1 Homepage

Table 1.1 Cable color description

| NO. | Description  |
|-----|--|
| 1   | Click this button to go back to the previous page  |
| 2   | Connection button<br>When device and robot arm are connected to network, click the button to connect the device to robot arm |
| 3   | Alarm log<br>You can click it to check alarm log   |

| NO. | Description   |
|-----|---|
| 4   | <p>Manager</p> <p>APP login personnel are divided into observer, operator, programmer and manager, different personnel can operate different functions, including the most authority of the management, can operate all functions</p> <ul style="list-style-type: none"> <li>• Observer: check the system status, I/O status, robot pose, and alarms</li> <li>• Operator: Operate a robot based on the existing scripts without programming</li> <li>• Programmer: Program, Teach</li> <li>• Manager: Set parameters</li> </ul> |
| 5   | Monitoring module shortcuts   |
| 6   | Set speed ratio   |
| 7   | <p>Robotic arm enable button</p> <p>The icon is green when robot motor is in the enabled status</p> <p>The icon is red when robot motor is in the disabled status</p>   |
| 8   | <p>Emergency stop switch</p> <p>Emergency stop switch can be pressed when robot arm is in short of time during operation, to control servo drive power off and robot arm stop urgently but constant power</p>   |
| 9   | <p>System settings</p> <p>Click this button to expand the page to view help documentation, lock screen, switch skins, etc.</p>  |
| 10  | <p>Jogging robotic arm</p> <p>You can jogging the robot arm. Click the button  to switch the joint coordinate system or the Cartersin coordinate system</p>  |
| 11  | <p>Programming module</p> <p>Programming modules are mainly used for editing and running programs</p>   |
| 12  | <p>Process</p> <p>Support drag teaching, conveyor tracking</p>  |
| 13  | <p>Setting</p> <p>Set the related parameters of robot arm, including motion parameters, coordinate system settings, calibration, etc.</p>   |

| NO. | Description  |
|-----|--|
| 14  | Monitoring module<br>You can view the status of robot arm, set the output of I/O , set the end parameters of robot arm and other functions |
| 15  | The 3D illustration of a robotic arm   |

**NOTICE**

The software supports the screen lock function. If the software has not been operated for a long time, the screen is automatically locked. The unlock password is 000000 by default.

## 2. Fast Connection

### Prerequisites

- The controller has been connected to the WiFi module.
- The APP supports WiFi function.

### Procedure

**Step 1** Search Dobot controller WiFi name and connect it. The WiFi name is prefixed with **Dobot\_WIFI\_XXX**. The default WiFi password is **1234567890**.

You can modify the WiFi password on **the Setting > Software Set > WiFi Set** page with manager authority.

**Step 2** Click **Connect** on the left pane of the APP.

### 3. Setting

Before teaching or running robot programs, a series of settings are required, including motion parameter setting, user mode selecting and process setting.

#### 3.1 Set Jog

You can set the velocity, acceleration or other parameters in different coordinate systems with programmer authority or manager authority when jogging a robot or running robot programs. After setting the parameters, please click **Save**.

Set the maximum velocity and acceleration in Joint and Cartesian coordinate system when jogging a robot. As shown in Figure 3.1.




Figure 3.1 Jogging parameters in the Joint coordinate system

#### 3.2 Set Playback

Set the maximum velocity, acceleration, and jerk in the Joint and Cartesian coordinate system when running robot programs, as shown in Figure 3.2.




Figure 3.2 Playback parameters

When doing jogging or playback, the method calculating the velocity and acceleration for each axis (in Joint or Cartesian coordinate system) is shown as follows.

- Actual jogging velocity = the maximum jogging velocity \* global velocity rate
- Actual jogging acceleration = the maximum jogging acceleration\* global velocity rate
- Actual playback velocity = the maximum playback velocity \* the set velocity rate in the velocity function
- Actual playback acceleration = the maximum playback acceleration \* the set acceleration rate in the acceleration function
- Actual playback jerk = the maximum playback jerk \* the set acceleration rate in the jerk function

#### NOTE

The rates (velocity rate, acceleration rate, or jerk rate) can be set in the related speed functions.

If the motion mode is **Jump** when running robot programs, you need to set **StartHeight**, **EndHeight**, and **zLimit**.

You can set 10 sets of Jump parameters. Please set and select any set of parameters for calling Jump command during programming.




Figure 3.3 Jump parameters

### 3.3 Coor User

When the position of workpiece is changed or a robot program needs to be reused in multiple processing systems of the same type, you can create coordinate systems on the workpiece to simplify programming. There are totally 10 groups of User coordinate systems, of which the first one is defined as the Base coordinate system by default and cannot be changed. And the others can be customized by users.

#### NOTICE

When creating a User coordinate system, please make sure that the reference coordinate system is the Base coordinate system.

- Point: move TCP to any point **A** to create origin, and create user coordinate system according to the default tool coordinate system As shown in Figure 3.4.




Figure 3.4 Point

- Line: Confirm a straight line by any two points **A** and **B**. The direction from A to B is defined as the positive direction of Y-axis, The Z-axis of Tool coordinate system of which point A is the origin is projected into the vertical plane that confirmed by points A and point B, we can define it as the positive direction of Z-axis. and then the positive direction X axis can be defined based on the right-hand rule. As shown Figure 3.5.




Figure 3.5 Line

- **Area:** User coordinate system is created by three-point calibration method. Move the robot to three points  $A(x_1, y_1, z_1)$ ,  $B(x_2, y_2, z_2)$ , and  $C(x_3, y_3, z_3)$ . Point A is defined as the origin and the line from point A to Point B is defined as the positive direction of X-axis. The line that point C is perpendicular to X-axis is defined as the position direction of Y-axis. And then the Z-axis can be defined based on the right-handed rule, as shown in Figure 3.6.




Figure 3.6 Area

Take the establishment of User 1 coordinate system as an example.

### Prerequisites

- The robot has been powered on.
- The robot is enabled.
- The robot is in the Cartesian coordinate system.
- The user's authority is programmer authority or manager authority.

### Procedures

**Step 1** Click **Coor User** on the **Setting** page. As shown Figure 3.7.




Figure 3.7 User coordinate system

- Step 2** Click **Aspect** and jog robot to the first point and click **GET** on the **First Point** section to get the first point.
- Step 3** Jog robot to the second point and click **GET** on the **Second Point** to get the second point.
- Step 4** Jog robot to the third point and click **GET** on the **Third Point** to get the third point.
- Step 5** Click **ADD** and **SAVE** to create User 1 coordinate system.
- Step 6** Click **Change coordinate** on the APP and select **UserCoordinate to NO 1**. If the icon **NO.0** turns into **NO.1**, you can use the User 1 coordinate system for teaching and programming.

### 3.4 Coor Tool

When an end effector such as welding gun, gripper is mounted on the robot, the Tool coordinate system is required for programming and operating a robot. For example, you can use multiple grippers to carry multiple workpieces simultaneously to improve the efficiency by setting each gripper to a Tool coordinate system.

There are totally 10 groups of Tool coordinate systems. Tool 0 coordinate system is the predefined Tool coordinate system which is located at the robot flange and cannot be changed.

### NOTICE

When creating a Tool coordinate system, please make sure that the reference coordinate system is the predefined Tool coordinate system.

Tool coordinate system is created by three-point calibration method (TCP +ZX): After the end effector is mounted, please adjust the direction of the end effector, to make TCP (Tool Center Point) align with the same point (reference point) in three different directions, for obtaining the position offset of the end effector, and then jog the robot to the other three points (**A**, **B**, **C**) for obtaining the angle offset, as shown in Figure 3.8.




Figure 3.8 Three points calibration method (TCP+ZX)

Take the establishment of Tool 1 coordinate system as an example.

#### Prerequisites

- The robot has been powered on.
- The robot is enabled.
- The robot is in the Cartesian coordinate system.
- The user's authority is programmer authority or manager authority.

#### Procedure

- Step 1** Mount an end effector on the robot. The detailed instructions are not described in this

topic.

**Step 2** Click **Tool coordinate** on the **Setting** page. As shown Figure 3.9.




Figure 3.9 Tool Coordinate page

#### NOTE

**Rx, Ry, Rz** are the orientation data, which are designated by rotating the tool center point (TCP) around the X, Y, Z axes under the selected Tool coordinate system.

- Step 3** Click **Position**, Jog the robot to the reference point in the first direction, then click **GET** on the **First Point** section to get the coordinates of the first point.
- Step 4** Jog the robot to the reference point in the second direction, then click **GET** on the **Second Point** section to get the coordinates of the second point.
- Step 5** Jog the robot to the reference point in the third direction, then click **GET** on the **Third Point** section to get the coordinates of the third point.
- Step 6** Jog the robot to the reference point (point **A**) in the vertical direction, then click **GET** on the **First Point** section to get the fourth point.
- Step 7** Jog the Z-axis to a point (point **B**) along the positive direction, then click **GET** on the **Second Point** section to get the fifth point  
This step defines the Z-axis.
- Step 8** Jog the X-axis to another point (point **C**), then click **GET** on the **Third Point** section to get the sixth point  
The three points (A, B, C) cannot lie in the same line.  
This step defines the X-axis, and the Y-axis can be defined based on the right-handed rule.
- Step 9** Click **ADD** and **SAVE** to create Tool 1coordinate system.

**Step 10** Click **Change coordinate** on the APP and select **ToolCoordinate** to **NO.1**. If the If the icon **NO.0** turns into **NO.1**, you can use the User 1 coordinate system for teaching and programming.

### 3.5 Safe Set

In the safety setting module, you can set safety parameters such as collision detection, power control, joint braking, etc.

This module must be operated with the programmer authority or manager authority.

#### 3.5.1 Safe Collision

Collision detection is mainly used for reducing the impact on the robot arm, to avoid damage to the robot arm or external equipment. If the collision detection is activated, the robot arm will stop running automatically when the robot arm hits an obstacle.

You can enable collision detection function on the **Setting > Safe Set > Safe Collision** page and set the collision level. Meanwhile, you can select **Turn on automatic drag after collision**, namely, when the robot arm stops running after hitting an obstacle, you can drag robot to a safe position.




Figure 3.10 Safety Hit

#### 3.5.2 Electronic Skin

Electronic skin allows robot to respond in real time when robot meets an obstacle, helping robot avoid obstacle during running.

You can enable electronic skin function on the **Setting > Safe Set > Electronic skin** page and set the robot status when meeting an obstacle. For example, robot can bypass the obstacle or stop running. You can also set the electronic skin parameters on this page




Figure 3.11 Safety Hit

| Parameter             | Description                           |
|-----------------------|---------------------------------------|
| Avoid speed           | Range: 1~500, recommend value: 100    |
| Avoid distance        | Range: 0~200, recommend value: 80     |
| Avoid acceleration    | Range: 1~50000, recommend value:1000  |
| Recovery speed        | Range: 1~500, Recommend value: 100    |
| Recovery acceleration | Range: 1~50000, Recommend value: 1000 |

### 3.5.3 Joint Brake

If you want to drag joints by hand, please enable the braking function. Namely, Open each joint brake on the **Setting > Safe Set > Joint brake** page. When enable this function, please hold the robot arm to avoid damage.




Figure 3.12 Joint brake

### 3.5.4 Power Control

When the emergency stop switch is pressed, the robot will power off. You can click Power On on the **Setting > Safe Set > Power control** page to power on the robot. Also, you can power off the robot on this page.




Figure 3.13 Power control

### 3.5.5 Terminal Load

To ensure optimum robot performance, it is important to make sure the load and inertia of the

end effector are within the maximum rating for the robot.

The load is weight of the end effector and work piece, which must not exceed the maximum load. You can set the load on the **Setting > Safe Set > Terminal load** page.




Figure 3.14 Terminal load

## 3.6 Remote Control

External equipment can send commands to a robot by different remote control modes, such as remote I/O mode and remote Modbus mode. The default mode is Teaching mode when the robot is shipped out. When you need to set the remote mode, please set it on APP with the robot motor in the disabled state.



### NOTICE

- Robot rebooting is not required when switching the remote mode.
- The emergency stop switch on the hardware is always available no matter what mode the robot system is in.
- Please DO NOT switch the remote mode when the robot is running in the current remote mode. You need to exit the current mode and then switch to the other remote mode. Namely, please stop the robot running and then switch the mode.

### 3.6.1 Remote I/O

When the remote mode is I/O mode, external equipment can control a robot in this mode. The specific I/O interface descriptions are shown in Table 3.1.

Table 3.1 Specific I/O interface description

| I/O interface                | Description |
|------------------------------|-------------|
| Input (For external control) |             |

| I/O interface                      | Description                          |
|------------------------------------|--------------------------------------|
| DI 11                              | Clear alarm                          |
| DI 12                              | Continue to run                      |
| DI 13                              | Pause running in the I/O mode        |
| DI 14                              | Stop running and exit the I/O mode   |
| DI 15                              | Start to run in the I/O mode         |
| DI 16                              | Emergency stop and exit the I/O mode |
| Output (For displaying the status) |                                      |
| DO 13                              | Ready status                         |
| DO 14                              | Pause status                         |
| DO 15                              | Alarm status                         |
| DO 16                              | Running status                       |



### NOTICE

All input signals are low to high.

### Prerequisites

- The project to be running in the remote mode has been prepared.
- The external equipment has been connected to the robot system by the I/O interface. The specific I/O interface description is shown in Table 3.1.
- The robot has been powered on.
- The user's authority is programmer authority or manager authority.

### NOTE

The details on how to connect external equipment and use it are not described in this topic.

### Procedure

#### Step 1 Click Setting > Remote Control.

The remote control page is displayed, as shown in Figure 3.15.




Figure 3.15 Remote control page

**Step 2** Select **IO** on the **Remote Control** page and select the offline project on the **Select Offline Project** section. Click **SAVE**.

Right now, only the emergency stop button and the real-time coordinates displaying section are available.

**Step 3** Trigger the starting signal on the external equipment.

The robot will move as the selected offline project. If the stop signal is triggered, the remote I/O mode will be invalid.

### 3.6.2 Remote Modbus

When the remote mode is Modbus mode, external equipment can control a robot in this mode.

Table 3.2 Specific Modbus register description

| Register address (Take a PLC as an example) | Register address (Robot system) | Description                                 |
|---|---------------------------------|---|
| <b>Coil register</b>                        |                                 |   |
| 00001                                       | 0                               | Start running in the remote Modbus mode     |
| 00002                                       | 1                               | Pause running in the remote Modbus mode     |
| 00003                                       | 2                               | Continue to run                             |
| 00004                                       | 3                               | Stop to run and exit the remote Modbus mode |

| Register address (Take a PLC as an example) | Register address (Robot system) | Description                                    |
|---|---------------------------------|--|
| 00005                                       | 4                               | Emergency stop and exit the remote Modbus mode |
| 00006                                       | 5                               | Clear alarm                                    |
| Discrete input register                     |                                 |  |
| 10001                                       | 0                               | Auto-exit                                      |
| 10002                                       | 1                               | Ready status                                   |
| 10003                                       | 2                               | Pause status                                   |
| 10004                                       | 3                               | Running status                                 |
| 10005                                       | 4                               | Alarm status                                   |

## Prerequisites

- The project to be running in the remote mode has been prepared.
- The robot has been connected to the external equipment with the Ethernet interface. You can connect them directly or via a router, please select based on site requirements.

The IP address of the robot system must be in the same network segment of the external equipment without conflict. The default IP address is 192.168.5.1.

- The robot has been powered on.
- The user's authority is programmer authority or manager authority.

### NOTE

The details on how to connect external equipment and use it are not described in this topic.

## Procedure

### Step 1 Click Setting > Remote Control.

The remote control page is displayed, as shown in Figure 3.16.



Figure 3.16 Remote control page

**Step 2** Select **Modbus** on the **Remote Control** page and select the offline project on the **Select Offline Project** section. Click **SAVE** and **LOAD**.

Right now, only the emergency stop button and the real-time coordinates displaying section are available.

**Step 3** Trigger the starting signal on the external equipment.

The robot will move as the selected offline project. If the stop signal is triggered, the remote Modbus mode will be invalid.

### 3.7 Robot Pose

APP supports to move robot to common points: package point, homing point, user-defined point. Moving robot to the package point can reduce the robot space, easy to pack and transport. Homing point is homing position. User-defined point is user-defined based on site requirements, which is convenient to move to this position quickly.

This module must be operated with the programmer authority or manager authority.





Figure 3.17 Posture setting



- Package Point: Click to move robot to the factory point.



- Home Point: Long press to move robot to the homing point.



- Custom Posture: Click to move robot to the user-defined point.

Before moving to the user-defined point, you need to define this point: Jog robot to this point, click **Get** and **Save**.

### 3.8 Installation

The default is that the robot is mounted on a flat table or floor, in which case no change is needed on this page. However, if the robot is ceiling mounted, wall mounted or mounted at an angle, you need to set the rotation angle and slop angle in the disabled status. This module must be operated with the manager authority.

Also, you can click **CALIBRATE** on the **Installation** page after installing the robot and enabling the robot motor, and operate the robot based on the tips(Jog robot in the joint coordinate system to make the end flange perpendicular up to the ground) shown on the **Installation** page, then click **Calibrate installation angle** to obtain the rotation angle and slope angle.

Slop angle is the angle that robot rotates counterclockwise around X-axis at the origin point.

Rotation angle is the angle that robot rotates counterclockwise around Z-axis at the origin point.




Figure 3.18 Installation setting

### 3.9 Manufactory Set

Generally, this module is used by Dobot support engineer or factory member with manager authority. The details will not be described in this topic.

### 3.10 Software Set

This module is operated with manager authority.

#### 3.10.1 Lock Set

You can set APP lock screen time or modify the locking password based on site requirements. If the software is not operated within this time period, the system will automatically lock the screen. The unlock password defaults to: 000000.




Figure 3.19 Setting lock time

### 3.10.2 File Import/Export

This function is used to import or export file from controller which can improve reusability.




Figure 3.20 Import/export file

### 3.10.3 WiFi Set

The robot system can be communicated with external equipment by the WiFi module. You can modify the WiFi name and password on the **Setting > Software Set > WiFi Set** page and then restart the controller to make effective. The default password is **1234567890**.




Figure 3.21 Set network

### 3.10.4 IP Setting

The robot system can be communicated with external equipment by the Ethernet interface which supports TCP, UDP and Modbus protocols. The default IP address is **192.16.5.1**. In real applications, if the TCP or UDP protocol is used, the robot system can be a client or a server based on site requirements; if the Modbus protocol is used, the robot system only can be the Modbus slave, and the external equipment is the master.

You can modify the IP address on the **Setting > Software Set > IP setting** page. The IP address of the robot system must be in the same network segment of the external equipment without conflict.




Figure 3.22 Setting controller IP

- If the robot system connects to the external equipment directly or with a switchboard, please select **Set IP address manually** and modify **IP Address**, **subnet mask**, **default gateway**, and then click **SAVE**.
- If the robot system connects to the external equipment with a router, please select **Obtain an IP address automatically** to assign IP address automatically, and then click **SAVE**.

### 3.10.5 User Manager

You can modify the observer, operator, programmer, and manager's password on the User manage page.




Figure 3.23 User manage

## 4. Process

This module must be operated with programmer authority or manager authority.

### 4.1 Drag Teach

You can drag robot to teach by APP or function keys on the end of robot.

Click **Craft > Drag teach**, the dragging page is displayed, as shown in Figure 4.1.




Figure 4.1 Hand-hold teach page

Table 4.1 Button description

| Button        | Description  |
|---------------|--|
| Start drag    | Click this button to open or close drag mode   |
| Save path     | Click this button to save trajectory   |
| Path playback | Click this button to start or stop playback.<br>Select the recorded trajectory, and click Path playback to start trajectory playback   |
| Advanced      | You can set the playback loop-time, speed override and decide whether to recur the trajectory as a constant speed<br><br>Speed override is that the playback speed is set to a multiple of the dragging speed, you can set to 0.25, 0.5, 1, 2, 4 |

#### NOTE

There are two kinds of trajectory names. For example, **01-01-00-20-07.csv** is a trajectory which records by APP. You can record multiple trajectories in this type. **Button\_drag\_track.csv** is a trajectory which records by clicking function keys on the end of robot. In this type, you can only record one trajectory.

## 4.2 Palletizing

In carrying applications, some parts are regularly arranged with uniform spacing and teaching part positions one by one results in a high error and poor efficiency. Palletizing process can resolve these problems.

A full palletizing process includes pallet parameters setting and pallet programming. After you set the pallet parameters on the teach pendant, the generated configuration file will be imported to the robot system automatically, then you can write a pallet program by calling pallet API based on site requirements.

### 4.2.1 Setting Pallet

Pallet parameter settings include basic parameter setting and path point setting. Basic parameter setting is to set pallet name, stack number, palletizing direction and stack spacing. Path points are the configured points on the assembly path or dismantling path.

- Transition point (point A): A point the robot must move to when assembling or dismantling stacks, which is fixed or varies with the pallet layer.
  - Preparation point (point B): A point calculated by the target point and the set offset.
- Target point (point C): The first stack point.

Figure 4.2 and Figure 4.3 show the assembly path and dismantling path.




Figure 4.2 Assembly path




Figure 4.3 Dismantling path

Stack indicates parts or products to be carried. Pallet indicates an object which places the stacks. Assembling stack indicates that the robot places stacks to the pallet as the configured pallet type. Dismantling stack indicates that the robot takes out stacks from the pallet as the configured pallet type. Pallet type indicates the layout of all stacks placed on the pallet. In our robot system, only the matrix pallet is supported, on which the stacks are placed in regular intervals, as shown in Figure 4.4.




Figure 4.4 Matrix pallet

In this topic, we describe how to set pallet parameters. The 10 types of pallets can be defined.

### Prerequisites

- The robot has been powered on.

- The suction cup or gripper kit has been mounted on the robot
- (Optional) The User coordinate system has been set on the pallet. When teaching positions, you can select the set User coordinate system based on site requirements.
- The robot motor has been enabled.
- The user's authority is programmer authority or higher authority.

### Procedure

**Step 1** Click **Palletizing** on the **Craft** page.

The pallet page is displayed, as shown in Figure 4.5.




Figure 4.5 Pallet page

**Step 2** Set the basic pallet parameters on the **Base set** tab.

Table 4.2 shows the basic pallet parameter description.

Table 4.2 Basic pallet parameter description

| Parameter | Description   |
|-----------|---|
| Name      | Pallet name   |
| Direction | Palletizing direction<br>Value: X->Y->Z or Y->X->Z<br>In this topic, we select <b>X-&gt;Y-&gt;Z</b> |
| Total     | Number of stacks in X, Y, Z direction respectively  |
| Offset    | Stack interval in X, Y, Z direction respectively  |

**Step 3** Jog the robot to the first stack position and click **GET COORDINATE** on the **Pallet** tab, as shown in Figure 4.6.

**User Coordinate** is the User coordinate system index, which needs to be consistent with the User coordinate system selected during teaching.




Figure 4.6 Teach the first stack position

**Step 4** Jog the robot to the transition point and click **GET COORDINATE** on the **Transition Point** tab, as shown in Figure 4.7.

**User coordinate** is the User coordinate system index, which needs to be consistent with the User coordinate system selected during teaching.

If **Change with layer height** is selected, the transition point is varied with the pallet layer. If not, it is the fixed point.




Figure 4.7 Teach the transition point

**Step 5** Jog the robot to the position where is above the first stack, and click **GET COORDINATE** on the **Prepare Point** tab.

**User coordinate** is the User coordinate system index, which needs to be consistent with the User coordinate system selected during teaching.

**Step 6** Click **ADD** to generate the configuration file and import to the robot system automatically.

#### 4.2.2 Example

After setting the pallet parameters, you can call pallet API for programming. This topic takes stack assembly as an example to describe.

Program 4.1 Stack assembly demo

```
local MPpick = MatrixPallet(0,1, "IsUnstack=true Userframe=8")           // Define the pallet instance
Reset(MPpick)                                                               // Initial the pallet instance
while true do
    MoveIn(MPpick,"velAB=90 velBC=50")                                     // Start to assemble
    MoveOut(MPpick)
    result=IsDone(MPpick)
    if (result == true)                                                       // Check whether stack assembly is
complete
        then
            print("EXIT ...")
            break
        end
    end
Release(MPpick)                                                               // Release pallet instance
```

## 5. Monitor

### 5.1 I/O Monitor

You can set or monitor the I/O status of the controller and robot on this page, as shown in Figure 5.1, you can monitor I/O status with the observer authority. Also, you can set the output with the operator authority or higher authority.




Figure 5.1 I/O Monitor

There are three features: Output, monitor and simulation.

- Output: Set the digital output or analog output with the operator authority or higher authority.
- Monitor: Check the status of the input and output with the observer authority or higher authority. The status of the output and input cannot be modified.
- Simulation: Simulate the analog input in the manual mode or auto mode for debugging and running program with the operator authority or higher authority, as shown in Figure 5.2.




Figure 5.2 Simulation

## 5.2 Robot Status

You can check data of the robot, joint load, and running log.

| Data                      |       | Run Log  |       |
|---------------------------|-------|--|-------|
| Controller temperature    | 0°C   | SEARCH   | CLEAR |
| Mains voltage             | 0.32V | 2020-11-17 17:26:45 Change IO output.3   |       |
| Average power consumption | 0.04W | 2020-11-17 17:26:50 Connection error!!!  |       |
| Robot current             | 0.12A | 2020-11-17 17:26:50 Id:24581 Type:controller Reason: AC Status detection error |       |
| Tool Current              | 0.0mA | 2020-11-17 17:27:51 Connect device   |       |
| Joint load                |       | 2020-11-17 17:29:21 Connection error!!!  |       |
| Joint 1                   | 0°C   | 2020-11-17 17:29:52 Connect device   |       |
| Joint 2                   | 0°C   | 2020-11-17 17:30:08 Connect device   |       |
| Joint 3                   | 0°C   | 2020-11-17 18:31:06 Disconnect device  |       |
| Joint 4                   | 0°C   | 2020-11-17 18:31:08 Disconnect device  |       |
| Joint 5                   | 0°C   | 2020-11-17 18:31:30 Connect device   |       |
| Joint 6                   | 0°C   | 2020-11-17 18:33:33 Stop joint change  |       |
|                           |       | 2020-11-17 18:33:34 Stop joint change  |       |
|                           |       | 2020-11-17 18:33:40 Change coordinate: Tool:No.0 User:No.0                     |       |
|                           |       | 2020-11-17 18:33:40 Change power status:Enable                                 |       |
|                           |       | 2020-11-17 18:35:09 Emergency stop   |       |
|                           |       | 2020-11-17 18:35:14 Change power status:Disable                                |       |
|                           |       | 2020-11-17 18:35:39 Id:12296 Type:controller Reason:Ontology of electricity    |       |
|                           |       | 2020-11-17 18:35:39 Id:12288 Type:controller Reason:Emergency stop detected    |       |

Figure 5.3 Robot status

## 5.3 Terminal

This module must be operated with programmer authority or manager authority.

### 5.3.1 Custom End

You can install gripper plug-in, enable and control it on the **Monitor > Terminal > Custom end** page.

In this topic, we take DH gripper as an example to describe.

**Step 1** Click  on the **Monitor > Terminal > Custom end** page to install DH gripper.




Figure 5.4 Install DH gripper

**Step 2** Click **Custom end > DH-V2 > Setting**.

The **Setting** page is displayed.




Figure 5.5 Setting page

**Step 3** Set **Baud** to 115200 and click **Init** on the **Setting** page.

**Step 4** Set the gripper opening and closing position and force on the Control page.




Figure 5.6 Control DH gripper

### 5.3.2 Terminal Hot Key

After installing the gripper, you can set the end-effector shortcut key on this page, so that you can control the gripper by the **control end effector** button on the end of the robot.




Figure 5.7 Terminal hot key

## 6. Programming

This module must be operated with the programmer authority or manager authority.

### 6.1 Project Description

The robot program is managed in project form, including teaching points list, global variables, and program files. Figure 6.1 shows the project structure.




Figure 6.1 Project structure

### 6.2 Program Description

CR5 robot supports script programming and blockly programming which use the Lua language as the programming language.




Figure 6.2 Program Description




Figure 6.3 Programming process

- **Script Programming**

Script programming uses Lua as the programming language, as shown in Figure 6.4.




Figure 6.4 Script programming

Table 6.1 Button description

| Button   | Description                                       |
|--|---|
|  edit               | Write program                                     |
|  teach              | Set teaching points                               |
|  Fx <sup>+</sup>    | Command area, you can program with those commands |
|                     | Undo  |
|                     | Recover   |
|                    | Go back to the beginning of a line                |
|                   | Go back to the end of a line                      |
|                   | Align code  |
| <br>Manage thread | Delete thread                                     |
| <br>Add thread    | Add thread. Up to 5 threads can be added          |
|  save             | Save program                                      |

- **Blockly Program**

Blockly is graphical programming. The operation of the robot can be programmed through puzzles which is intuitive and easy to understand. Only one thread is supported when using Blockly.




Figure 6.5 Blockly programming

### 6.3 Program Example

This section takes script programming as an example to describe how to program. We call **Go** command to make the robot move between point P1 and point P2 circularly.

#### Prerequisites

Robot has connected to APP.

Robot has been enabled.

#### Procedure

**Step 1** Click **Program> Script program> New File**, select template and name this project.




Figure 6.6 Select project template and name the project

The program page is displayed, as shown in Figure 6.7.




Figure 6.7 Script program page

**Step 2** Click **Fx<sup>+</sup>**, choose **MOVE>Speed** and set speed to 40%.




Figure 6.8 Set speed

**Step 3** Jog robot to a point and click **⊕** to add the point **P1** on the **Point** page. Jog robot to another point and click **⊕** to add the point **P2**. The saved points are shown in Figure 6.9.

**Arm** is the arm orientation, **Tool** is tool coordinate system, **User** is User coordinate system.




Figure 6.9 Save teaching points

Table 6.2 Button description

| Button | Description   |
|--------|---|
|        | Add a teaching point  |
|        | Delete a teaching point   |
|        | Cover a point<br>you can select a teaching point and click <b>Cover</b> to cover the current teaching point |
|        | Move to a point<br>Select a point, and long press this button to make robot move to this point              |
|        | Download teaching points  |

**Step 4** Click **Edit** to edit program, click to select **Move>Go**, add two Go commands and select Point P1 and P2 in the two **Go** commands respectively, as shown in Figure 6.10.




Figure 6.10 Edit program

```
1 Speed(40)
2 while(true)
3   do
4     Go(P1)
5     Go(P2)
6   end
```

Figure 6.11 Finish programming

**Step 5** Click **Save** in manual mode.

**Step 6** Set running speed and click to debug this program, the robot will move between point **P1** and point **P2**. Also, you can click to stop it.

Table 6.3 Button description

| Button  | Description   |
|---|---|
|  | Start button, click it to run program   |
|  | <p>Debug button</p> <p>Click once: Start to debug a program,  turns into </p> <p>Click twice: Start to run a program,  turns into </p> <p>If you need to pause the running program, please click </p> |
|  | Pause button, click it to pause program   |
|  | <p>Run a program step by step, you can run a program step by step by setting a breakpoint</p> <p>This button is valid only if  turns into </p>  |